




```

LL          IIIIII          SSSSSSSS
LL          IIIIII          SSSSSSSS
LL          II             SS
LL          II             SS
LL          II             SS
LL          II             SS
LL          II             SSSSSS
LL          II             SSSSSS
LL          II             SS
LL          II             SS
LL          II             SS
LL          II             SS
LL          II             SS
LLLLLLLLLLLL IIIIII          SSSSSSSS
LLLLLLLLLLLL IIIIII          SSSSSSSS

```



```

0000 1      .TITLE GLOBALS - GLOBAL DEFINITIONS FOR THE EXEC
0000 2      .IDENT 'V04-000'
0000 3
0000 4      *****
0000 5      *
0000 6      *  COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
0000 7      *  DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
0000 8      *  ALL RIGHTS RESERVED.
0000 9      *
0000 10     *  THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
0000 11     *  ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
0000 12     *  INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
0000 13     *  COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
0000 14     *  OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
0000 15     *  TRANSFERRED.
0000 16     *
0000 17     *  THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
0000 18     *  AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
0000 19     *  CORPORATION.
0000 20     *
0000 21     *  DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
0000 22     *  SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
0000 23     *
0000 24     *
0000 25     *****
0000 26
0000 27     MODIFIED BY:
0000 28
0000 29     V03-004 BLS0152      Benn Schreiber      22-Feb-1982
0000 30     Remove $SHRDEF
0000 31
0000 32
0000 33     $DYNDEF GLOBAL      ;DYNAMIC DATA STRUCTURE DEFINITIONS
0000 34     $FCBDEF GLOBAL     ;FILE CONTROL BLOCK DEFINITIONS
0000 35     $IPLDEF GLOBAL     ;PRIORITY LEVEL DEFINITIONS
0000 36     $PCBDEF GLOBAL     ;PROCESS CONTROL BLOCK DEFINITIONS
0000 37     $PRVDEF GLOBAL     ;PRIVILEGE BIT DEFINITIONS
0000 38     $PSLDEF GLOBAL     ;PROCESSOR STATUS LONG WORD DEFINITIONS
0000 39     $RSNDEF GLOBAL     ;RESOURCE NUMBER DEFINITIONS
0000 40     $VADEF GLOBAL      ;VIRTUAL ADDRESS DEFINITIONS
0000 41
0000 42     .END

```


GLOBALS
Symbol table

- GLOBAL DEFINITIONS FOR THE EXEC N 2

16-SEP-1984 00:13:38 VAX/VMS Macro V04-00
5-SEP-1984 03:42:23 [SYS.SRC]GLOBALS.MAR;1

Page 2
(1)

DYN\$C_ACB = 00000002 G
DYN\$C_ACL = 0000003F G
DYN\$C_ADP = 00000001 G
DYN\$C_AQB = 00000003 G
DYN\$C_BOOTCB = 00000006 G
DYN\$C_BRDCST = 0000001A G
DYN\$C_BUFIO = 00000013 G
DYN\$C_CDB = 00000033 G
DYN\$C_CDRP = 00000039 G
DYN\$C_CD_BBRPG = 00000002 G
DYN\$C_CD_Cddb = 00000001 G
DYN\$C_CD_SHDW_WRK = 00000003 G
DYN\$C_CEB = 00000004 G
DYN\$C_CHIP = 00000048 G
DYN\$C_CI = 00000061 G
DYN\$C_CIA = 00000045 G
DYN\$C_CIDG = 0000003B G
DYN\$C_CIMSG = 0000003C G
DYN\$C_CI_BDT = 00000001 G
DYN\$C_CI_FQDT = 00000002 G
DYN\$C_CLASSDRV = 00000064 G
DYN\$C_CLU = 00000065 G
DYN\$C_CLU_BT X = 00000004 G
DYN\$C_CLU CLUB = 00000003 G
DYN\$C_CLU CLUDCB = 00000005 G
DYN\$C_CLU CLUOPT = 00000006 G
DYN\$C_CLU CLUVEC = 00000002 G
DYN\$C_CLU CSB = 00000001 G
DYN\$C_CLU LCKDIR = 00000007 G
DYN\$C_CONF = 00000007 G
DYN\$C_CRB = 00000005 G
DYN\$C_CST = 00000008 G
DYN\$C_CXB = 0000001B G
DYN\$C_DCCB = 00000027 G
DYN\$C_DDB = 00000006 G
DYN\$C_DPT = 0000001E G
DYN\$C_ERP = 0000003A G
DYN\$C_EXTGSD = 00000028 G
DYN\$C_FCB = 00000007 G
DYN\$C_FRK = 00000008 G
DYN\$C_GSD = 00000015 G
DYN\$C_IDB = 00000009 G
DYN\$C_INIT = 00000063 G
DYN\$C_IRP = 0000000A G
DYN\$C_IRPE = 0000002C G
DYN\$C_JIB = 0000002F G
DYN\$C_JNL = 00000067 G
DYN\$C_JNLWCB = 00000024 G
DYN\$C_JNL_ABL = 00000001 G
DYN\$C_JNL_ACBM = 00000004 G
DYN\$C_JNL_ADL = 00000002 G
DYN\$C_JNL_BCB = 00000003 G
DYN\$C_JNL_BUF = 00000005 G
DYN\$C_JNL_BXSTS = 00000013 G
DYN\$C_JNL_CWQ = 00000010 G
DYN\$C_JNL_DB = 00000006 G
DYN\$C_JNL_DIOREAD = 00000015 G

DYN\$C_JNL_JMT = 00000009 G
DYN\$C_JNL_MSG = 00000012 G
DYN\$C_JNL_MSGDATA = 00000014 G
DYN\$C_JNL_NDL = 00000008 G
DYN\$C_JNL_RC = 00000011 G
DYN\$C_JNL_RCPC = 0000000C G
DYN\$C_JNL_RM = 0000000A G
DYN\$C_JNL_RRP = 0000000B G
DYN\$C_JNL_RUL = 0000000D G
DYN\$C_JNL_SFT = 00000007 G
DYN\$C_JNL_VCL = 0000000E G
DYN\$C_JNL_VLE = 0000000F G
DYN\$C_JPB = 0000001F G
DYN\$C_KFD = 00000043 G
DYN\$C_KFE = 00000018 G
DYN\$C_KFPB = 00000044 G
DYN\$C_KFRH = 00000026 G
DYN\$C_LC_CHREML = 00000006 G
DYN\$C_LC_CLS = 00000005 G
DYN\$C_LC_FPEMUL = 00000007 G
DYN\$C_LC_MP = 00000003 G
DYN\$C_LC_MSCP = 00000008 G
DYN\$C_LC_SCS = 00000004 G
DYN\$C_LC_SYSL = 00000009 G
DYN\$C_LKB = 00000035 G
DYN\$C_LKID = 00000037 G
DYN\$C_LNM = 00000040 G
DYN\$C_LOADCODE = 00000062 G
DYN\$C_LOG = 0000000B G
DYN\$C_LPD = 00000034 G
DYN\$C_MBX = 0000002B G
DYN\$C_MPWMAP = 00000004 G
DYN\$C_MTL = 00000019 G
DYN\$C_MVL = 00000016 G
DYN\$C_NDB = 0000001C G
DYN\$C_NET = 00000017 G
DYN\$C_NON_PAGED = 00000001 G
DYN\$C_ORB = 00000049 G
DYN\$C_PAGED = 00000002 G
DYN\$C_PBH = 00000020 G
DYN\$C_PCB = 0000000C G
DYN\$C_PCBVEC = 00000001 G
DYN\$C_PDB = 00000021 G
DYN\$C_PFB = 00000047 G
DYN\$C_PFL = 00000023 G
DYN\$C_PGD = 00000066 G
DYN\$C_PGD_F11BC = 00000001 G
DYN\$C_PHVEC = 00000002 G
DYN\$C_PIB = 00000022 G
DYN\$C_PMB = 00000046 G
DYN\$C_PQB = 0000000D G
DYN\$C_PRCMAP = 00000005 G
DYN\$C_PTR = 00000025 G
DYN\$C_RBM = 00000031 G
DYN\$C_RIGHTSLIST = 00000042 G
DYN\$C_RSB = 00000036 G
DYN\$C_RSHT = 00000038 G

IMG
V04-

GLOBALS
Symbol table

- GLOBAL DEFINITIONS FOR THE EXEC B 3

16-SEP-1984 00:13:38 VAX/VMS Macro V04-00
5-SEP-1984 03:42:23 [SYS.SRC]GLOBALS.MAR;1

Page 3
(1)

DYN\$C_RVT = 0000000E G
DYN\$C_SCS = 00000060 G
DYN\$C_SCS_CDL = 00000001 G
DYN\$C_SCS_CDT = 00000002 G
DYN\$C_SCS_DIR = 00000003 G
DYN\$C_SCS_HQB = 0000000B G
DYN\$C_SCS_PB = 00000004 G
DYN\$C_SCS_PDT = 00000005 G
DYN\$C_SCS_RDT = 00000006 G
DYN\$C_SCS_SB = 00000007 G
DYN\$C_SCS_SPNB = 00000009 G
DYN\$C_SCS_SPPB = 00000008 G
DYN\$C_SCS_UQB = 0000000A G
DYN\$C_SHB = 0000002A G
DYN\$C_SHMCEB = 0000002E G
DYN\$C_SHMGSD = 00000029 G
DYN\$C_SHRBUF10 = 00000080 G
DYN\$C_SLAVCEB = 0000002D G
DYN\$C_SPECIAL = 00000080 G
DYN\$C_SSB = 0000001D G
DYN\$C_SUBTYPE = 00000060 G
DYN\$C_SWPMAP = 00000003 G
DYN\$C_TQE = 0000000F G
DYN\$C_TWP = 00000030 G
DYN\$C_TYPAHD = 00000014 G
DYN\$C_UCB = 00000010 G
DYN\$C_UNUSED_2 = 00000041 G
DYN\$C_VCA = 00000032 G
DYN\$C_VCB = 00000011 G
DYN\$C_WCB = 00000012 G
DYN\$C_WQE = 0000003E G
DYN\$C_XWB = 0000003D G
FCB\$B_ACCLKMODE = 0000000B G
FCB\$B_FID_NMX = 00000029 G
FCB\$B_FID_RVN = 00000028 G
FCB\$B_TYPE = 0000000A G
FCB\$C_LENGTH = 000000B4 G
FCB\$K_LENGTH = 000000B4 G
FCB\$L_ACCLKID = 00000048 G
FCB\$L_ACLBL = 00000084 G
FCB\$L_ACLFL = 00000080 G
FCB\$L_CACHELKID = 00000054 G
FCB\$L_DIRINDX = 000000B0 G
FCB\$L_EFBLK = 0000003C G
FCB\$L_EXFCB = 0000000C G
FCB\$L_FCBBL = 00000004 G
FCB\$L_FCBFL = 00000000 G
FCB\$L_FILEOWNER = 00000058 G
FCB\$L_FILESIZE = 00000038 G
FCB\$L_GRP_PROT = 00000078 G
FCB\$L_HDLBN = 00000034 G
FCB\$L_HIGHWATER = 00000044 G
FCB\$L_LOCKBASIS = 0000004C G
FCB\$L_OWN_PROT = 00000074 G
FCB\$L_STLBN = 00000030 G
FCB\$L_STVBN = 0000002C G
FCB\$L_SYS_PROT = 00000070 G

FCB\$L_TRUNCVBN = 00000050 G
FCB\$L_WLBL = 00000014 G
FCB\$L_WLFL = 00000010 G
FCB\$L_WOR_PROT = 0000007C G
FCB\$Q_ACMODE = 00000068 G
FCB\$R_MAX_CLASS_PROT = 0000009C G
FCB\$R_MIN_CLASS_PROT = 00000088 G
FCB\$R_ORB = 00000058 G
FCB\$S_ACMODE = 00000008 G
FCB\$S_FCBDEF = 000000B4 G
FCB\$S_FID = 00000006 G
FCB\$S_MAX_CLASS_PROT = 00000014 G
FCB\$S_MIN_CLASS_PROT = 00000014 G
FCB\$S_ORB = 00000058 G
FCB\$V_BADACL = 00000007 G
FCB\$V_BADBLK = 00000002 G
FCB\$V_DELAYTRNC = 00000009 G
FCB\$V_DIR = 00000000 G
FCB\$V_ERASE = 00000006 G
FCB\$V_EXCL = 00000003 G
FCB\$V_MARKDEL = 00000001 G
FCB\$V_RMSLOCK = 00000005 G
FCB\$V_SPOOL = 00000004 G
FCB\$V_STALE = 00000008 G
FCB\$W_ACNT = 0000001A G
FCB\$W_DIRSEQ = 00000042 G
FCB\$W_FID = 00000024 G
FCB\$W_FID_NUM = 00000024 G
FCB\$W_FID_RVN = 00000028 G
FCB\$W_FID_SEQ = 00000026 G
FCB\$W_FILEPROT = 00000070 G
FCB\$W_LCNT = 0000001E G
FCB\$W_REFCNT = 00000018 G
FCB\$W_SEGN = 0000002A G
FCB\$W_SIZE = 00000008 G
FCB\$W_STATUS = 00000022 G
FCB\$W_TCNT = 00000020 G
FCB\$W_UICGROUP = 0000005A G
FCB\$W_UICMEMBER = 00000058 G
FCB\$W_VERSIONS = 00000040 G
FCB\$W_WCNT = 0000001C G
IPL\$_ASTDEL = 00000002 G
IPL\$_HWCLK = 00000018 G
IPL\$_IOPOST = 00000004 G
IPL\$_MAILBOX = 0000000B G
IPL\$_PERFMON = 0000000F G
IPL\$_POWER = 0000001F G
IPL\$_QUEUEAST = 00000006 G
IPL\$_SCHED = 00000003 G
IPL\$_SCS = 00000008 G
IPL\$_SYNCH = 00000008 G
IPL\$_TIMER = 00000008 G
IPL\$_TIMERFORK = 00000007 G
PCB\$B_ASTACT = 0000000C G
PCB\$B_ASTEN = 0000000D G
PCB\$B_AUTHPRI = 0000002B G
PCB\$B_DPC = 0000002A G

IMG3
V04-

GLOBALS
Symbol table

- GLOBAL DEFINITIONS FOR THE EXEC

C 3

16-SEP-1984 00:13:38 VAX/VMS Macro V04-00
5-SEP-1984 03:42:23 [SYS.SRC]GLOBALS.MAR;1

Page 4
(1)

PCBSB_PGFLINDEX = 0000005A G
PCBSB_PRI = 0000000B G
PCBSB_PRI8 = 0000002F G
PCBSB_PRI8SAV = 00000029 G
PCBSB_PRI8AV = 00000028 G
PCBSB_TYPE = 0000000A G
PCBSB_WFC = 0000002E G
PCBSK_LENGTH = 00000120 G
PCBSK_LENGTH = 00000120 G
PCBSL_ACLBL = 00000100 G
PCBSL_ACLFL = 000000FC G
PCBSL_ARB = 0000008C G
PCBSL_ASTQBL = 00000014 G
PCBSL_ASTQFL = 00000010 G
PCBSL_DEFPROT = 00000114 G
PCBSL_DLCKPRI = 0000010C G
PCBSL_EFC2P = 00000058 G
PCBSL_EFC3P = 0000005C G
PCBSL_EFCS = 00000050 G
PCBSL_EFCU = 00000054 G
PCBSL_EFWM = 0000004C G
PCBSL_EOWNER = 00000068 G
PCBSL_EPID = 00000064 G
PCBSL_IPAST = 00000110 G
PCBSL_JIB = 00000080 G
PCBSL_LOCKQBL = 00000108 G
PCBSL_LOCKQFL = 00000104 G
PCBSL_OWNER = 0000001C G
PCBSL_PHD = 0000006C G
PCBSL_PHYPCB = 00000018 G
PCBSL_PID = 00000060 G
PCBSL_PMB = 0000011C G
PCBSL_PQB = 0000004C G
PCBSL_SQBL = 00000004 G
PCBSL_SQFL = 00000000 G
PCBSL_STS = 00000024 G
PCBSL_SWAPSIZE = 0000005C G
PCBSL_UIC = 000000BC G
PCBSL_WAITIME = 00000118 G
PCBSL_WSSWP = 00000020 G
PCBSL_WTIME = 00000028 G
PCBSM_ASTPEN = 00020000 G
PCBSM_BATCH = 00004000 G
PCBSM_DELPEN = 00000002 G
PCBSM_DISAWS = 01000000 G
PCBSM_EPID_WILD = 80000000 G
PCBSM_FORCPEN = 00000004 G
PCBSM_HIBER = 00080000 G
PCBSM_INQUAN = 00000008 G
PCBSM_INTER = 02000000 G
PCBSM_LOGIN = 00100000 G
PCBSM_NETWORK = 00200000 G
PCBSM_NOACNT = 00008000 G
PCBSM_NODELET = 00800000 G
PCBSM_PHDRES = 00040000 G
PCBSM_PSWAPM = 00000010 G
PCBSM_PWRAS = 00400000 G

PCBSM_RECOVER = 04000000 G
PCBSM_RES = 00000001 G
PCBSM_RESPEN = 00000020 G
PCBSM_SECAUDIT = 03000000 G
PCBSM_SSFEXC = 00000040 G
PCBSM_SSFEXCE = 00000080 G
PCBSM_SSFEXCS = 00000100 G
PCBSM_SSFEXCU = 00000200 G
PCBSM_SSRWAIT = 00000400 G
PCBSM_SUSPEN = 00000800 G
PCBSM_SWPVB = 00010000 G
PCBSM_WAKPEN = 00001000 G
PCBSM_WALL = 00002000 G
PCBSQ_PRIV = 00000084 G
PCBSM_EPID_NODE_IDX = 00000008 G
PCBSM_EPID_NODE_SEQ = 00000002 G
PCBSM_EPID_PROC = 00000015 G
PCBSM_LNAME = 00000010 G
PCBSM_PCBDEF = 00000120 G
PCBSM_PRIV = 00000008 G
PCBSM_TERMINAL = 00000008 G
PCBST_LNAME = 00000070 G
PCBST_TERMINAL = 00000044 G
PCBSV_ASTPEN = 00000011 G
PCBSV_BATCH = 0000000E G
PCBSV_DELPEN = 00000001 G
PCBSV_DISAWS = 00000018 G
PCBSV_EPID_NODE_IDX = 00000015 G
PCBSV_EPID_NODE_SEQ = 0000001D G
PCBSV_EPID_PROC = 00000000 G
PCBSV_EPID_WILD = 0000001F G
PCBSV_FORCPEN = 00000002 G
PCBSV_HIBER = 00000013 G
PCBSV_INQUAN = 00000003 G
PCBSV_INTER = 00000019 G
PCBSV_LOGIN = 00000014 G
PCBSV_NETWORK = 00000015 G
PCBSV_NOACNT = 0000000F G
PCBSV_NODELET = 00000017 G
PCBSV_PHDRES = 00000012 G
PCBSV_PSWAPM = 00000004 G
PCBSV_PWRAS = 00000016 G
PCBSV_RECOVER = 0000001A G
PCBSV_RES = 00000000 G
PCBSV_RESPEN = 00000005 G
PCBSV_SECAUDIT = 0000001B G
PCBSV_SSFEXC = 00000006 G
PCBSV_SSFEXCE = 00000007 G
PCBSV_SSFEXCS = 00000008 G
PCBSV_SSFEXCU = 00000009 G
PCBSV_SSRWAIT = 0000000A G
PCBSV_SUSPEN = 0000000B G
PCBSV_SWPVB = 00000010 G
PCBSV_WAKPEN = 0000000C G
PCBSV_WALL = 0000000D G
PCBSW_APTCNT = 00000030 G
PCBSW_ASTCNT = 00000038 G

IMGS
V04-

: 4
: 4
: 4

:

GLOBALS
Symbol table

- GLOBAL DEFINITIONS FOR THE EXEC D 3

16-SEP-1984 00:13:38 VAX/VMS Macro V04-00
5-SEP-1984 03:42:23 [SYS.SRC]GLOBALS.MAR;1

Page 5
(1)

PCBSW_BIOCNT = 0000003A G
PCBSW_BIOLM = 0000003C G
PCBSW_DIOCNT = 0000003E G
PCBSW_DIOLM = 00000040 G
PCBSW_GPGCNT = 00000034 G
PCBSW_GRP = 000000BE G
PCBSW_MEM = 000000BC G
PCBSW_MTXCNT = 0000000E G
PCBSW_PGFLCHAR = 00000058 G
PCBSW_PPGCNT = 00000036 G
PCBSW_PRCNT = 00000042 G
PCBSW_SIZE = 00000008 G
PCBSW_STATE = 0000002C G
PCBSW_TMBU = 00000032 G
PRVSM_ACNT = 00000200 G
PRVSM_ALLSPOOL = 00000010 G
PRVSM_ALTPRI = 00002000 G
PRVSM_BUGCHK = 00800000 G
PRVSM_BYPASS = 20000000 G
PRVSM_CMEEXEC = 00000002 G
PRVSM_CMKRNL = 00000001 G
PRVSM_DETACH = 00000020 G
PRVSM_DIAGNOSE = 00000040 G
PRVSM_EXQUOTA = 00080000 G
PRVSM_GROUP = 00000100 G
PRVSM_GRPNAM = 00000008 G
PRVSM_LOG_IO = 00000080 G
PRVSM_MOUNT = 00020000 G
PRVSM_NETMBX = 00100000 G
PRVSM_NOACNT = 00000200 G
PRVSM_OPER = 00040000 G
PRVSM_PFNMAP = 04000000 G
PRVSM_PHY_IO = 00400000 G
PRVSM_PRMCEB = 00000400 G
PRVSM_PRMGBL = 01000000 G
PRVSM_PRMGBX = 00000800 G
PRVSM_PSWAPM = 00001000 G
PRVSM_SETPRI = 00002000 G
PRVSM_SETPRV = 00004000 G
PRVSM_SHARE = 80000000 G
PRVSM_SHMEM = 08000000 G
PRVSM_SYSGBL = 02000000 G
PRVSM_SYSLCK = 40000000 G
PRVSM_SYSNAM = 00000004 G
PRVSM_SYSPRV = 10000000 G
PRVSM_TMPMBX = 00008000 G
PRVSM_VOLPRO = 00200000 G
PRVSM_WORLD = 00010000 G
PRVSS_PRVDEF = 00000005 G
PRVSV_ACNT = 00000009 G
PRVSV_ALLSPOOL = 00000004 G
PRVSV_ALTPRI = 0000000D G
PRVSV_BUGCHK = 00000017 G
PRVSV_BYPASS = 0000001D G
PRVSV_CMEEXEC = 00000001 G
PRVSV_CMKRNL = 00000000 G
PRVSV_DETACH = 00000005 G

PRVSV_DIAGNOSE = 00000006 G
PRVSV_DOWNGRADE = 00000021 G
PRVSV_EXQUOTA = 00000013 G
PRVSV_GROUP = 00000008 G
PRVSV_GRPNAM = 00000003 G
PRVSV_GRPDRV = 00000022 G
PRVSV_LOG_IO = 00000007 G
PRVSV_MOUNT = 00000011 G
PRVSV_NETMBX = 00000014 G
PRVSV_NOACNT = 00000009 G
PRVSV_OPER = 00000012 G
PRVSV_PFNMAP = 0000001A G
PRVSV_PHY_IO = 00000016 G
PRVSV_PRMCEB = 0000000A G
PRVSV_PRMGBL = 00000018 G
PRVSV_PRMJNL = 00000025 G
PRVSV_PRMGBX = 0C00000B G
PRVSV_PSWAPM = 0000000C G
PRVSV_READALL = 00000023 G
PRVSV_SECURITY = 00000026 G
PRVSV_SETPRI = 0000000D G
PRVSV_SETPRV = 0000000E G
PRVSV_SHARE = 0000001F G
PRVSV_SHMEM = 0000001B G
PRVSV_SYSGBL = 00000019 G
PRVSV_SYSLCK = 0000001E G
PRVSV_SYSNAM = 00000002 G
PRVSV_SYSPRV = 0000001C G
PRVSV_TMPJNL = 00000024 G
PRVSV_TMPMBX = 0000000F G
PRVSV_UPGRADE = 00000020 G
PRVSV_VOLPRO = 00000015 G
PRVSV_WORLD = 00000010 G
PSLSC_EXEC = 00000001 G
PSLSC_KERNEL = 00000000 G
PSLSC_SUPER = 00000002 G
PSLSC_USER = 00000003 G
PSLSM_C = 00000001 G
PSLSM_CM = 80000000 G
PSLSM_CURMOD = 03000000 G
PSLSM_DV = 00000080 G
PSLSM_FPD = 08000000 G
PSLSM_FU = 00000040 G
PSLSM_IPL = 001F0000 G
PSLSM_IS = 04000000 G
PSLSM_IV = 00000020 G
PSLSM_N = 00000008 G
PSLSM_PRVMOD = 00C00000 G
PSLSM_SAFBITS = 000037FF G
PSLSM_TBIT = 00000010 G
PSLSM_TP = 40000000 G
PSLSM_V = 00000002 G
PSLSM_Z = 00000004 G
PSLSS_CURMOD = 00000002 G
PSLSS_IPL = 00000005 G
PSLSS_PRVMOD = 00000002 G
PSLSS_PSLDEF = 00000004 G

IMGS
V04-

GLOBALS
Symbol table

- GLOBAL DEFINITIONS FOR THE EXEC E 3

16-SEP-1984 00:13:38 VAX/VMS Macro V04-00
5-SEP-1984 03:42:23 [SYS.SRC]GLOBALS.MAR;1

Page 6
(1)

PSLSV_C	= 00000000	G
PSLSV_CM	= 0000001F	G
PSLSV_CURMOD	= 00000018	G
PSLSV_DV	= 00000007	G
PSLSV_FPD	= 0000001B	G
PSLSV_FU	= 00000006	G
PSLSV_IPL	= 00000010	G
PSLSV_IS	= 0000001A	G
PSLSV_IV	= 00000005	G
PSLSV_N	= 00000003	G
PSLSV_PRVMOD	= 00000016	G
PSLSV_TBIT	= 00000004	G
PSLSV_TP	= 0000001E	G
PSLSV_V	= 00000001	G
PSLSV_Z	= 00000002	G
RSNS_ASTWAIT	= 00000001	G
RSNS_BRKTHRU	= 00000006	G
RSNS_CLUSTRAN	= 0000000E	G
RSNS_IACLOCK	= 00000007	G
RSNS_JQUOTA	= 00000008	G
RSNS_LOCKID	= 00000009	G
RSNS_MAILBOX	= 00000002	G
RSNS_MAX	= 0000000F	G
RSNS_MPLEMPTY	= 0000000B	G
RSNS_MPWBUSY	= 0000000C	G
RSNS_NPDYNMEM	= 00000003	G
RSNS_PGDYNMEM	= 00000005	G
RSNS_PGFILE	= 00000004	G
RSNS_SCS	= 0000000D	G
RSNS_SWPFILE	= 0000000A	G
VASM_BYTE	= 000001FF	G
VASM_P1	= 40000000	G
VASM_SYSTEM	= 80000000	G
VASM_VPG	= FFFFFFFE00	G
VASM_VPN	= 3FFFFFFE00	G
VASS_BYTE	= 00000009	G
VASS_VADEF	= 00000004	G
VASS_VPG	= 00000017	G
VASS_VPN	= 00000015	G
VASV_BYTE	= 00000000	G
VASV_P1	= 0000001E	G
VASV_SYSTEM	= 0000001F	G
VASV_VPG	= 00000009	G
VASV_VPN	= 00000009	G

+-----+
! Psect synopsis !
+-----+

PSECT name	Allocation		PSECT No.	Attributes															
ABS	00000000	(	0.)	00	(	0.)	NOPIC	USR	CON	ABS	LCL	NOSHR	NOEXE	NORD	NOWRT	NOVEC	BYTE		
\$ABSS	00000000	(	0.)	01	(	1.)	NOPIC	USR	CON	ABS	LCL	NOSHR	EXE	RD	WRT	NOVEC	BYTE		


```

+-----+
! Performance indicators !
+-----+

```

Phase	Page faults	CPU Time	Elapsed Time
-----	-----	-----	-----
Initialization	35	00:00:00.04	00:00:01.88
Command processing	134	00:00:00.51	00:00:04.52
Pass 1	200	00:00:04.80	00:00:16.04
Symbol table sort	0	00:00:00.63	00:00:02.54
Pass 2	46	00:00:00.88	00:00:02.72
Symbol table output	59	00:00:00.37	00:00:00.64
Psect synopsis output	2	00:00:00.02	00:00:00.02
Cross-reference output	0	00:00:00.00	00:00:00.00
Assembler run totals	479	00:00:07.26	00:00:28.37

The working set limit was 1350 pages.
25262 bytes (50 pages) of virtual memory were used to buffer the intermediate code.
There were 30 pages of symbol table space allocated to hold 500 non-local and 0 local symbols.
42 source lines were read in Pass 1, producing 33 object records in Pass 2.
15 pages of virtual memory were used to define 14 macros.

```

+-----+
! Macro library statistics !
+-----+

```

Macro library name	Macros defined
-----	-----
-\$255\$DUA28:[SYS.OBJ]LIB.MLB;1	6
-\$255\$DUA28:[SYSLIB]STARLET.MLB;2	5
TOTALS (all libraries)	11

587 GETS were required to define 11 macros.

There were no errors, warnings or information messages.

MACRO/LIS=LIS\$:GLOBALS/OBJ=OBJ\$:GLOBALS MSRC\$:GLOBALS/UPDATE=(ENH\$:GLOBALS)+EXECMLS/LIB

0375 AH-BT13A-SE
VAX/VMS V4.0

DIGITAL EQUIPMENT CORPORATION
CONFIDENTIAL AND PROPRIETARY

